



Continental HHT Update Client


Instructions to Update the
Hand-Held Tool

(for externals)

Download and Update Installation Instructions

1. Download Installation File

- › Download zip file.
- › If download of the zip-file was blocked by fire-wall / virus scanner:
 - › Download the “alternate zip file”.
 - › After successful download, change (rename) extension of the downloaded file from .zi1 to .zip
- › Unzip the file “HHT-update-client__yyyy-mm-dd.zip”
- › Use “conti” as password for unzipping if necessary.
- › At the end there should be the folder “HHT-update-client__yyyy-mm-dd” on your computer with the following content:




2. Installation

- › Ensure you have admin rights on your computer, before starting the installation process.
- › Install the drivers: Press right mouse click on the file „driver.exe“, to “Run as administrator”.
- › Do not connect the HHT during the installation.
- › Afterwards, install „Setup_HHT-update-client.exe“

3. Update Process

- › Open “Hand-Held Tool Update Client” software and follow the instructions displayed. The update client will update itself on every launch.



- › The update client will automatically download the latest Hand-Held Tool software from the internet and stores in the PC. An offline update is possible with the downloaded software packages.
- › In case the Hand-Held Tool
 - › has a Firmware version is inferior to 6.8 or (check menu “Setup → Release” on your Hand-Held Tool device)
 - › is not detected or is not responsive

Then follow the instructions below


- › Power off the device (if not possible, press the reset button)
- › Keep the ESC button pressed, connect the USB cable to the PC and to the Hand-Held Tool
- › Launch the “Hand-Held Tool Update Client” software and follow the instructions displayed.

3. Settings for internet connection (Proxy settings)

- › If the Hand-Held Tool Update Client shows “No internet connection ...”, check the proxy settings on the update client.
- › In case of using an VPN-connection or working in a company network the correct proxy settings might be required.

4. Problems with Memory Card

- › If problems on memory card are detected, click on “Close symbol” or “Continue without scanning” to avoid any interruptions to the software update tool.



5. Troubleshooting

- › The client might hang or not detect the Hand-Held Tool due to the following reasons:
 - › Application is run without drivers being installed.
 - › Defective USB cable
 - › Unstable USB connection due to some software issues on the computer.
 - › Earlier update process interrupted.

- › Resolve the problem:
 - › The user should close the application and restart it again.
 - › Try a different USB port.
 - › If the behavior is still the same, install USB drivers which are provided along with the installation files of the HHT Update Client.

Continental Reifen Deutschland GmbH

Büttnerstraße 25

30165 Hannover

Germany

www.continental-truck-tires.com

www.continental-corporation.com

Continental 
The Future in Motion